

AppComponent

Package Slide Show

User Manual

Ver 1.2.0.0
6th April, 2015
TerraSky co., Ltd

Content

1. Preface.....	3
2. Notice	3
(1) Conditions of Use	3
(2) Request to the customer	3
(3) Trademarks.....	3
(4) Support Policy	3
3. Slide Show AppComponent Package	4
(1) Installation	4
(2) Slide Show.....	4
a. Display components on Studio	5
1. Fixed Image Slide Show	7
2. Fixed Image Slide Show (With Thumbnails)	9
3. Chatter Image Slide Show.....	11
4. Chatter Image Slide Show (With Thumbnails)	13

1. Preface

This document covers information related to an AppExchange AppComponent to be used in SkyVisualEditor. AppComponents are made using the SkyVisualEditor API and Visualforce Pages and Apex classes. For more information about these please refer to documentation from Salesforce.

2. Notice

(1) Conditions of Use

You may only make use of the functionality listed in this manual if you satisfy one of the following conditions.

- ✓ You have contracted to use license(s) of SkyVisualEditor
- ✓ You are evaluating SkyVisualEditor during the 30 day trial

(2) Request to the customer

Unauthorized reproduction of this manual is forbidden. Although every attempt has been made to ensure quality of this manual, if you find any problems or errors please let us know. Use the contents of this manual at your own risk. TerraSky cannot be held responsible for any trouble, lawsuit, etc. resulting either directly or indirectly from the use of this manual. We reserve the right to update this manual at any time without warning.

(3) Trademarks

TerraSky, the TerraSky logo, SkyVisualEditor and the SkyVisualEditor logo are registered trademarks of TerraSky co., Ltd. Salesforce.com, AppExchange and the “no software” logo are registered trademarks of salesforce.com, Inc., and salesforce.com owns other registered and unregistered trademarks. Other names used herein may be trademarks of their respective owners.

(4) Support Policy

The functionality listed in this manual is considered an official functionality of SkyVisualEditor and is supported the same as internal SkyVisualEditor functionality.

3. Slide Show AppComponent Package

Four different types of AppComponent are available in this Package.

No	AppComponent name
1	Fixed Image Slide Show
2	Fixed Image Slide Show(with Thumbnails)
3	Chatter Image Slide Show
4	Chatter Image Slide Show(with Thumbnails)

(1) Installation

Find the AppComponent package from the URL below and install it into your salesforce organization.

Version:1.2

- ✓ Install to Product environment (Production / Developer Edition)
<https://login.salesforce.com/packaging/installPackage.apexp?p0=04ti0000000H8x7>
- ✓ Install to Sandbox Environment
<https://test.salesforce.com/packaging/installPackage.apexp?p0=04ti0000000H8x7>

The following configuration on Salesforce organization is required to use this component.

- Chatter Settings -> Enable Chatter
- Salesforce CRM content -> Enable Salesforce CRM Content


(2) Slide Show

This component displays various images as Slide Show. Images can be selected from below.

- ✓ Chatter Files
- ✓ User specified URL
 - Static resource file within Salesforce Organization
 - Files outside of the Salesforce Organization

a. Display components on Studio

Once you have installed the package, login to the SkyVisualEditor Studio. This feature is available if an icon “SkyVisualEditor (Slide Show)” appears on the component panel.



b. Layout Components


「Slide Show」AppComponent」 can be placed in areas listed below.

Layout	available area
Salesforce Layout	--Directly under the Canvas. -Within the Page Block. -Within Panel Grid
Free Layout	-Directly under the Canvas -Within the Page Block -Within the Panel Grid
Dashboard Layout	-Directly under the Canvas. -Within the Flexible Panel.


*Note: Pages in PDF cannot be displayed.

Set the component on to the Studio screen to get exactly the same location on to your Salesforce screen after deploy.


[Studio Screen image]



[After Deploy; Salesforce screen image]



[Example of using Slide Show AppComponent]





Account		Opportunity	
Account Name		Name	Amount
United Oil & Gas Corp.		Edge SLA	\$80,000.00
sForce		Grand Hotels Kitchen Generator	\$15,000.00
Grand Hotels & Resorts Ltd		Grand Hotels SLA	\$90,000.00
Express Logistics and Transport		Express Logistics Portable Truck Generators	\$80,000.00
University of Arizona		Express Logistics SLA	\$120,000.00
Burlington Textiles Corp of America		Express Logistics Standby Generator	\$220,000.00
Pyramid Construction Inc.		University of AZ Installations	\$100,000.00
Dickenson plc		University of AZ Portable Generators	\$50,000.00
GenePoint			
United Oil & Gas, UK			

Los Angeles



New York



1. Fixed Image Slide Show



Specify the image URL for the Slide Show.


This component will not display thumbnail view.

i. Property Setting for the component

SlideShowStatic	
ID	Component1
Top(Y)	50
Left(X)	50
Width[px]	400
Display Settings	
Width Setting	☐
Image URLs	...
Auto-scroll through im	☒
Auto-scroll speed (sec)	5
Transition animation	fade ▼
Loop the Slide Show	☒
Display navigation Cor	☒
Display next / back bu	☒
Automatically adjust h	☐

"Component Property" will appear on the right hand side of the Studio Screen by clicking the icon on the canvas.

Name	Description
ID	Component ID defined in SkyVisualEditor
coordinates of position (Y)	Sets the coordinates of position (Y-axis) This property is available for Free Layout only.
coordinates of position (X)	Sets the coordinates of position (X-axis) This property is available for Free Layout only.
Width[px]	Sets the width of component
Specify Width	The image size will output in 100% of its size if the check is turned "off." If the check box is turned on; image size width can be adjusted in pixels. Default setting is "off".

Name	Description
Image URL [mandatory]	Specify the image URL for the Slide Show. Images can be specified from static resource in Salesforce Organization or files outside of Salesforce Organization. A message box with image URL will appear when you click the  button.  Select file from static resource. <pre>{!\$Resource.SAMPLE}</pre> Select zip file from static resource. <pre>{!URLFOR(\$Resource.ZIPFILE, 'SAMPLE.jpg')}</pre>
Automatic Page Switch	Set to switch images automatically. Default setting is “on”
Speed of Page Switch (sec)	Set the speed of page switch interval. Default setting is 5 seconds
Page Switch Animation	Set the animation for Page Switch -Fade -Slide
Loop the Slide Show	Set the Slide Show to Loop. Default setting is “on”
Display Navigation Control	Display Navigation Control at the bottom of the Slide Show Default setting is “on”
Display forward/rewind slide button	Display forward/rewind button next to the image. Default setting is “on”
Self-adjust height	Size of the component will self-adjust to the original size of the each image if the check is turned on. The image size (height) will be fixed to the largest size of the image. Default setting is “off”

2. Fixed Image Slide Show (With Thumbnails)



Specify the URL for images to use in Slide Show


Thumbnail will appear at the bottom of the Slide Show component.

i. Component Property Setting

SlideShowStaticWithCarousel	
ID	Component1
Top(Y)	50
Left(X)	50
Width[px]	400
Display Settings	
Width Setting	☐
Image URLs	...
Thumbnail width	100
Auto-scroll through im	☒
Auto-scroll speed (sec	5
Transition animation	fade
Loop the Slide Show	☒
Display next / back bu	☒
Automatically adjust h	☐

"Component Property" will appear on the right hand side of the Studio Screen by clicking the icon on the canvas.

Name	Description
ID	Component ID defined in SkyVisualEditor
coordinates of position (Y)	Sets the coordinates of position (Y-axis) This property is available for Free Layout only
Location Axis (X)	Sets the coordinates of position (X-axis) This property is available for Free Layout only.
Width[px]	Set the width of component
Specify Width	The image size will output in 100% of its size if the check is turned "off." You can specify the image size (in pixel) if the check is turned "on." "Default setting is turned "off"

Image URL [mandatory]	Set the URL for images used in Slide Show. The images can be static images from the Salesforce Organization or external files. Click the  button to display dialogue box to input the image URL  Specify file from static resource. <pre>{!\$Resource.SAMPLE}</pre> Specify ZIP file from static resource. <pre>{!URLFOR(\$Resource.ZIPFILE, 'SAMPLE.jpg')}</pre>
Thumbnail image width [mandatory]	Set Thumbnail image width.
Auto-scroll through image	Set to switch images automatically Default setting is “on”
Auto-scroll speed (sec)	Set the speed of page switch interval. Default Setting is 5 seconds.
Transaction animation	Set the animation for Page Switch. -Fade -Slide
Loop the Slide Show	Set the Slide Show to Loop Default setting is “on”
Display forward/rewind slide button	Display forward/rewind button next to the image Default setting is “on”
Self-adjust height	Size of the component will self-adjust to the original size of the each image if the check is turned on. The image size (height) will be fixed to the largest size of the image. Default setting is “off”

3. Chatter Image Slide Show



Specified Chatter image files can be used to display as Slide Show.

Thumbnail does not show in this component.

i. Component Property Setting

SlideShowChatter	
ID	Component1
Top(Y)	50
Left(X)	50
Width[px]	400
Display Settings	
Width Setting	☐
GroupId	...
Display Group feed co	☐
Number of images to d	
Auto-scroll through im	☒
Auto-scroll speed (sec	5
Transition animation	fade
Loop the Slide Show	☒
Display navigation Cor	☒
Display next / back bu	☒
Automatically adjust h	☐

"Component Property" will appear on the right hand side of the Studio Screen by clicking the icon on the canvas. Click icon on a canvas to show "Component

Name	Description
ID	Component ID defined in SkyVisualEditor
coordinates of position (Y)	Sets the coordinates of position (Y-axis) This property is available for Free Layout only.
coordinates of position (X)	Sets the coordinates of position (X-axis) This property is available for Free Layout only.
Width[px]	Set the width of component
Specify Width	The image size will output in 100% of its size if the check is turned "off." You can specify the image size (in pixel) if the check is turned "on."

Name	Description
GroupId	Set the Chatter Group ID. This will allow the users to select and display only the Chatter feeds and images with comments that are posted on a specific group. If the value is not set, all of the image files on the Chatter will become a subject for display.
Display Group feed comment	Select to display the selected Chatter feed and comments on the slideshow by Group ID. If the Group ID is not set, this setting will be invalid. Default setting is “off”
Number of images to display [Mandatory]	Set the number of images that can be retrieved from Chatter File.
Automatic Page Switch	Set to switch images automatically. Default setting is “on”
Speed of Page Switch (sec)	Set the speed of page switch interval. Default setting is 5 seconds.
Page Switch Animation	Set the animation for Page Switch.” -Fade –Slide
Loop the Slide Show	Set the Slide Show to Loop. Default setting is “on”
Display Navigation Control	Display Navigation Control at the bottom of the Slide Show. Default setting is “on”
Display forward/rewind slide button	Display forward/rewind button next to the image Default setting is “on”
Self-adjust height	Size of the component will self-adjust to the original size of the each image if the check is turned on. The image size (height) will be fixed to the largest size of the image. Default setting is “off”

4. Chatter Image Slide Show (With Thumbnails)



Specified Chatter image files can be used to display as Slide Show. Thumbnail will show at the bottom of the thumbnail.

i. Component Property Setting

SlideShowChatterWithCarousel	
ID	Component1
Top(Y)	50
Left(X)	50
Width[px]	400
Display Settings	
Width Setting	☐
GroupId	...
Display Group feed co	☐
Number of images to	
Thumbnail width	100
Auto-scroll through im	☒
Auto-scroll speed (sec	5
Transition animation	fade
Loop the Slide Show	☒
Display next / back bu	☒
Automatically adjust h	☐

"Component Property" will appear on the right hand side of the Studio Screen by clicking the icon on the canvas.

Name	Description
ID	Component ID defined in SkyVisualEditor
coordinates of position (Y)	Sets the coordinates of position (Y-axis) This property is available for Free Layout only.
coordinates of position (X)	Sets the coordinates of position (X-axis) This property is available for Free Layout only.
Width[px]	Set the width of component
Specify Width	The image size will output in 100% of its size if the check is turned "off." You can specify the image size (in pixel) if the check is turned "on."

Name	Description
GroupId	Set the Chatter Group ID. This will allow the users to select and display only the Chatter feeds and images with comments that are posted on a specific group. If the value is not set, all of the image files on the Chatter will become a subject for display.
Display Group feed comment	Select to display the selected Chatter feed and comments on the slideshow by Group ID. If the Group ID is not set, this setting will be invalid. Default setting is "off"
Number of images to display [Mandatory]	Set the number of images that can be retrieved from Chatter File.
Thumbnail image width [mandatory]	Set Thumbnail image width.
Auto-scroll through image	Set to switch images automatically Default setting is "on"
Auto-scroll speed (sec)	Set the speed of page switch interval.Default setting is 5 seconds
Transaction animation	Set the animation for Page Switch. -Fade -Slide
Loop the Slide Show	Set the Slide Show to Loop. Default setting is "on"
Display forward/rewind slide button	Display forward/rewind button next to the image Default setting is "on"
Self-adjust height	Size of the component will self-adjust to the original size of the each image if the check is turned on. The image size (height) will be fixed to the largest size of the image. Default setting is "off"